


# Orchard Spray Rates

How to Determine the Amount of Pesticide  
and Water to Use in Your Orchard





# Contents

## Background:

Types of Orchard Pesticide Applications .....	1
Orchards Then and Now .....	1
Dilute Applications .....	2
Low-Volume or Concentrate Applications .....	2
Tree-Row Volume .....	3

## Calculations for Dilute Applications ..... 3

How much <b>water</b> is needed for a dilute application? .....	3
Method 1: Experience .....	4
Method 2: Tree-row volume chart .....	4
Method 3: Tree-row volume equations .....	4

How much <b>pesticide</b> is needed for a dilute application? .....	7
---	---

## Calculations for Concentrate Applications ..... 8

How much <b>water</b> is needed for a concentrate application? .....	8
--	---

How much <b>pesticide</b> is needed for a concentrate application? .....	9
Method 1: Use per-acre rate on the label .....	9
Method 2: Use full rate by the standard conversion .....	10
Method 3: Use full rate less 20% .....	12
Method 4: Use customized rate by tree-row volume .....	13
Method 5: Use customized rate and percentage of standard .....	14

## Examples for Review ..... 15

## Spraying in Different Seasons and in Different Orchards ..... 18

## Summary ..... 18

## Acknowledgments ..... 18

## Appendix 1: Tree-Row Volume Chart ..... 19

## Appendix 2: Summary of How Much Water and Pesticide to Use ..... 20

## Appendix 3: Glossary of Terms ..... 21

**Author:** Celeste Welty, Extension Entomologist, The Ohio State University



Copyright © 2001, Ohio State University Extension

All educational programs conducted by Ohio State University Extension are available to clientele on a nondiscriminatory basis without regard to race, color, creed, religion, sexual orientation, national origin, gender, age, disability or Vietnam-era veteran status.

Keith L. Smith, Associate Vice President for Agricultural Administration and Director, OSU ExtensionTDD No. 800-589-8292 (Ohio only) or 614-292-1868

2/2001—2M—Leshner

## Background: Types of Orchard Pesticide Applications

Pesticide rates for fruit crops are listed in several different ways on labels for various pesticide products. These differences are sometimes confusing to novice fruit growers and even to experienced growers. In our Ohio tree fruit spray guide, insecticide and fungicide products are listed with rates given two ways — one column lists the amount of pesticide product *per 100 gallons* of water, and one column lists the amount of pesticide product *per acre*. How to decide which of these two rates to use to determine appropriate amounts of pesticide and water to use for a specific orchard is explained in detail in this bulletin.

Most reference books on fruit spraying show just one way of determining pesticide rates. This can leave the reader wondering if other methods are incorrect or just less preferred. In this bulletin, several methods are presented that should include most of the variations in spray rate calculations that fruit growers normally hear about. Recommendations for using each method are presented along with the advantages and disadvantages of each method.

### Orchards Then and Now

It helps us understand why rates are given in different ways if we consider the history of fruit growing and fruit spraying. Looking at the history helps us to see how pesticide rate recommendations have come about.

In the early decades of this century, apple trees were large and widely spaced within the orchard; horticulturalists still refer to large trees as *standard trees*. The old sprayers were handgun type sprayers that thoroughly covered the trees with the spray mix until drops began to drip from the leaves, which is what we call “to the point of runoff.”

To treat large standard apple trees to the point of runoff, the general rule was to use 400 gallons of spray mix per acre. All of the older pesticide recommendations were given as a rate of product per 100 gallons of water, with the understanding that it would take 400 gallons of spray mix to treat one acre of apple trees or pear trees.

For crops other than apple, the same principle applies but with different volumes. For peach, plum, and cherry, 300 gallons per acre is the standard dilute volume. For strawberries, brambles, blueberries, and grapes, 200 gallons per acre is the standard dilute volume.

Two major factors have changed since the old days. First, modern sprayers can adequately cover an acre of large trees with much less than 400 gallons per acre because coverage to the point of runoff is not needed for control of most arthropod pests and diseases. Second, few orchards now have large standard trees that take 400 gallons of spray mix per acre to treat to the point of runoff. Most commercial orchards



Figure 1. Hand-held application

now use dwarfing rootstocks. Dwarf or semidwarf trees are much smaller and more closely spaced than the old standard trees, and it takes less water to cover the dwarf or semidwarf trees.

### *Dilute Applications*

In our Ohio tree fruit spray guide, we still list the pesticide rate per 100 gallons of water. This is the rate that should be used if the grower needs to make a *dilute* application with either an airblast sprayer or a handgun sprayer. When a tank of pesticide is mixed at the dilute rate, the applicator should apply it to the trees until all parts of the tree are wet. This is what we call *spraying to the point of runoff*, that is, until water begins to drip off the leaves.

In many large commercial orchards, the only time that a dilute application is used is for sprays of superior oil in the delayed-dormant period in the spring, when the entire surface of the apple tree needs to be covered for good control of European red mite. In some smaller orchards, dilute applications are sometimes used throughout the growing season. Larger orchards usually are not treated with many dilute applications because they are more time-consuming.

### *Low-Volume or Concentrate Applications*

Modern airblast sprayers, which are also known as speed sprayers, can cover fruit trees with much less than 400 gallons of spray mix per acre. Airblast sprayers produce fine droplets that cover foliage very well without the large amount of water needed to reach the point of runoff. Low-volume applications made with airblast sprayers are most commonly in the range of 40 to 80 gallons per acre.

Low-volume applications are also called *concentrate applications* because as the volume of water is decreased, there is a proportional increase in the concentration of pesticide, in order to apply the




Figure 2. Airblast sprayer driving between the rows.



needed amount of pesticide per acre. Low-volume orchard sprays are commonly concentrated to several times the dilute rate. If the fruit grower uses what is called a 3X concentration, the volume of water is reduced to one third of the dilute volume and therefore the pesticide is increased by three times the dilute rate. **Note:** The pesticide is increased by three times the dilute rate, not three times the concentrate rate!

When a 5X concentration is used, the volume is reduced to one fifth of the dilute volume and therefore the pesticide concentration is increased by five times the dilute rate. Orchard sprays in the range of 2X to 5X are common.

### *Tree-Row Volume*

Because dwarf and semidwarf types of fruit trees are smaller at maturity than the large standard types of fruit trees, a system known as tree-row volume has been developed to determine how much spray mix is needed to cover the smaller trees. Although tree-row volume might sound complicated to someone who has never used it, it is well worth the effort to learn about it, because it should result in more accurate coverage and likely in less pesticide use per acre compared to using the full rates of water and pesticide. Tree-row volume is used to determine both the dilute volume and the related concentrate rate of pesticide per acre.

## *Calculations for Dilute Applications*

### *How much water is needed for a dilute application ?*

If you want to make a *standard* dilute application, then use 400 gallons of water per acre.

Because most orchards do not need as much as 400 gallons per acre, you can *customize* the spray to a volume that is best for your orchard. Even if you never make dilute applications, you need to determine what your dilute volume should be, because it is the basis for calculating the amount of pesticide to use for concentrate applications.

Determining your dilute volume per acre means *determining how many gallons of water it should take to cover one acre of your trees to the point of runoff*, which is when water begins to drip off the leaves. This number is *your dilute volume*; it is likely to be in the range of 100 to 200 gallons per acre for modern types of apple trees.

You can determine your dilute volume of water per acre by any of three ways:

**Method 1. Experience.**

Try different volumes of water per acre with your sprayer in your orchard and observe which volume results in runoff.

**Method 2. Use a tree-row volume chart.**

Estimates of dilute volume of water per acre are shown in the chart on page 19. The chart is based on tree size and spacing. If tree size within an orchard block is variable, then choose the measurements for the average size of the larger trees. For any combination of tree size and spacing, the chart shows what the dilute spray volume should be. The dilute spray volume is based on the rule that it takes 0.7 to 1.0 gallon to treat 1,000 cubic feet of tree canopy to the point of runoff. A canopy volume of 1,000 cubic feet is a section that is 10 feet wide by 10 feet tall by 10 feet deep. Most growers with well-pruned trees can use the minimum dilute volume, which is 0.7 gallon per 1,000 cubic feet of tree canopy. The maximum dilute volume is 1.0 gallon per 1,000 cubic feet of tree canopy. The maximum dilute volume should be used in an unpruned orchard with a thick canopy.

For example, if your trees are about 12 feet wide and 10 feet tall in rows spaced 20 feet apart, the chart shows that you have a maximum of about 261,000 cubic feet of tree per acre. If these trees are relatively well-pruned, then your dilute volume will be about 183 gallons of water per acre, as shown in the column for Minimum. If these trees are not pruned, then your dilute volume will be about 261 gallons of water per acre, as shown in the column for Maximum.

**Method 3. Use tree-row volume equations.**

If your tree size and spacing are not in the chart on page 19, then use the formulas given here.

*Tree-row volume* is canopy width, times tree height, times row length per acre. Row length per acre is 43,560 square feet per acre divided by the distance between rows, in feet. This number can be considered the maximum volume of trees this size.




Figure 3.  
Orchard measurements

Tree-row volume = (canopy width) x (tree height) x (row length per acre)

$$\text{Tree-row volume [cu. ft./acre]} = \left( \frac{\text{tree canopy diameter [feet]}}{\text{[feet]}} \right) \times \left( \frac{\text{tree height [feet]}}{\text{[feet]}} \right) \times \left( \frac{43,560 \text{ sq.ft./acre}}{\text{distance between rows [feet]}} \right)$$

For example, for trees 10 feet wide and 8 feet tall in rows 18 feet apart:

$$\begin{aligned} \text{Tree-row volume} &= 10 \text{ ft.} \times 8 \text{ ft.} \times \left( \frac{43,560 \text{ sq. ft. per acre}}{18 \text{ ft.}} \right) \\ &= 80 \times 2,420 = 193,600 \text{ cu. ft.} \end{aligned}$$

*Minimum dilute spray volume* is your tree-row volume per acre times 0.7 gallon per 1,000 cubic feet. Use this as your dilute volume of water per acre, if your trees are well pruned.

$$\text{Minimum dilute spray volume [gal./acre]} = \left( \frac{\text{your tree-row volume [cu. ft./acre]}}{\text{[cu. ft./acre]}} \right) \times \left( \frac{0.7 \text{ gal.}}{1,000 \text{ cu.ft.}} \right)$$

Use this as your dilute volume of water per acre if your trees are well pruned.

Continuing the example just given:

$$\text{Minimum dilute volume} = \left( 193,600 \text{ cu. ft.} \right) \times \left( \frac{0.7 \text{ gal.}}{1,000 \text{ cu. ft.}} \right) = 136 \text{ gal. per acre}$$

*Maximum dilute spray volume* is your tree row volume per acre times 1.0 gallon per 1,000 cubic feet. Use this as your dilute volume of water per acre if your trees are not well pruned.

$$\begin{array}{l} \text{Maximum dilute} \\ \text{spray volume} \\ \text{[gal./acre]} \end{array} = \left( \frac{\text{your tree-row volume}}{\text{[cu. ft./acre]}} \right) \times \left( \frac{1.0 \text{ gal.}}{1,000 \text{ cu. ft.}} \right)$$

Use this as your dilute volume of water per acre if your trees are not well pruned.

Continuing the example just given,

$$\begin{array}{l} \text{Maximum} \\ \text{dilute} \\ \text{volume} \end{array} = \left( 193,600 \text{ cu. ft.} \right) \times \left( \frac{1.0 \text{ gal.}}{1,000 \text{ cu. ft.}} \right) = 194 \text{ gal. per acre}$$

### *Optional Adjustments for Method 3*

#### *1. Canopy Thickness*

Canopy thickness can be factored into tree-row volume calculations. You will need to choose a density factor *between* 0.7 and 1.0, depending on the relative canopy density or tree shape, rather than using either the minimum or maximum volume as described previously. However, many orchardists have found that such an adjustment does not make any difference, and in most commercial orchards 0.7 is a good choice. Only in a completely unpruned orchard would the full 1.0 density factor be needed.

#### *2. Pesticide Type*

Pesticide type can be factored into tree-row volume calculations. Multiply the dilute volume by certain percentages because some thinners require lower volume and some stop-drop materials require higher volume. For example, use 40–50% for Promalin and Pro-Vide and 70–90% for thinners used on varieties other than spur Red Delicious. Some stop-drop materials require higher volume; use 100–120% for Ethrel, for instance.

#### *3. Lower Limit*

Some applicators use a *lower limit* of 200 gallons per acre as the minimum dilute volume even when tree-row volume calculations show that a smaller volume should be adequate. Not all orchardists agree with this, but it could be considered in cases where a smaller number of gallons is used and control is not satisfactory.



## How much pesticide is needed for a dilute application?

The amount of pesticide to use per acre is the *dilute rate times the dilute volume*. The dilute rate is the amount of pesticide per 100 gallons of water. The dilute volume is either the full standard (maximum) of 400 gallons per acre, or a customized amount that is likely to be much smaller (100–200 gallons per acre) as described earlier.

$$\begin{aligned}\text{amount of product per acre} &= (\text{dilute rate}) \times (\text{dilute volume}) \\ &= \left( \frac{\text{amt. of pesticide}}{100 \text{ gal.}} \right) \times \left( \frac{\text{gallons of water}}{\text{acre}} \right)\end{aligned}$$

For example, two orchards of different-sized trees need a dilute application of Guthion 50WP, which is used at a dilute rate of 0.75 pound per 100 gallons.

In the orchard of large standard trees that requires 400 gallons to spray to the point of runoff, the amount of Guthion to use for a dilute spray is 0.75 pound Guthion per 100 gallons water, times 400 gallons water per acre, which equals 3.0 pounds Guthion per acre.

$$\left( \frac{0.75 \text{ pounds}}{100 \text{ gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{acre}} \right) = \frac{3.0 \text{ pounds Guthion}}{\text{acre}}$$

In the orchard of small trees that requires 120 gallons to spray to the point of runoff, the amount of Guthion to use for a dilute spray is 0.75 pound Guthion per 100 gallons water, times 120 gallons water per acre, which equals 0.9 pound Guthion per acre.

$$\left( \frac{0.75 \text{ pound}}{100 \text{ gal. water}} \right) \times \left( \frac{120 \text{ gal. water}}{\text{acre}} \right) = \frac{0.9 \text{ pound Guthion}}{\text{acre}}$$

For another example with the same two orchards, how much superior oil per acre is needed at half-inch green if the dilute rate is 2 gallons of oil per 100 gallons of water?

For the large trees in this example:

$$\left( \frac{2 \text{ gal. oil}}{100 \text{ gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{acre}} \right) = \frac{8 \text{ gal. of oil}}{\text{acre}}$$

For the small trees:

$$\left( \frac{2 \text{ gal. oil}}{100 \text{ gal. water}} \right) \times \left( \frac{120 \text{ gal. water}}{\text{acre}} \right) = \frac{2.4 \text{ gal. of oil}}{\text{acre}}$$

## Calculations for Concentrate Spraying

### *How much water is needed for a concentrate application?*

No calculations are needed for this step. You simply need to know from experience, or from experimenting, how many gallons of water per acre *your airblast sprayer* uses to adequately treat your orchard for a low-volume application, for whatever speed, pressure, and nozzle arrangement you prefer to use. This number of gallons of water per acre is your *concentrate volume*. It will probably be in the range of 40 to 80 gallons per acre.

A question sometimes asked is: What concentration should I use, 3X or 4X or 5X?

The answer: The exact concentration does not matter. If you want to calculate what your concentration is, you can do this without any knowledge of how much pesticide you will use. After you decide on the amount of water that is needed for dilute application (pages 4-6) and for concentrate application (above), then you can *calculate the concentration by dividing your dilute volume of water per acre by your concentrate volume of water per acre*.

$$\text{concentration} = \frac{\text{dilute volume of water per acre}}{\text{concentrate volume of water per acre}}$$

For example, if you need 180 gallons to treat to the point of runoff, but your airblast uses 60 gallons to make a low-volume application, then your concentration is 180 divided by 60, which equals 3; this is a 3X application.

$$\frac{180 \text{ gal. water/acre}}{60 \text{ gal. water/acre}} = 3 \quad \text{This is a 3X application.}$$

### ***How much pesticide is needed for a concentrate application?***

The amount of pesticide to use per acre for concentrate applications can be determined for all orchards in general, as shown in Methods 1, 2, and 3 which are explained later in the text. The amount of pesticide to use per acre for concentrate applications can be customized to a specific orchard, as explained in Methods 4 and 5.

Before describing these methods, an important general point is that in concentrate spraying in a specific orchard block, *the amount of pesticide per acre stays constant even if the amount of water changes*. The rate of pesticide per acre is completely independent of the concentration used. For example, if you have an old sprayer that applies 75 gallons per acre and a new sprayer that applies 50 gallons per acre, you will use the same amount of pesticide per acre in either sprayer, although the mix in the old sprayer with 75 gallons will be a weaker concentration than the mix in the new sprayer with 50 gallons.

#### ***Method 1: Use the “amount per acre” rate as given on the label.***

The easiest decision about how much pesticide to use per acre is when a pesticide label states the rate *only* as an amount of product per acre, to be used regardless of whether the spray volume is high or low. For these products, we list their rates in our Ohio tree fruit spray guide only as an amount per acre, with no listing in the column for amount per 100 gallons.

For example, Savey 50WP on apples is used at 3 ounces per acre, whether in 25 gallons per acre or in 400 gallons per acre. For another example, Pounce 25WP on apples is used at 6 to 12 ounces per acre whether in 25 gallons per acre or in 400 gallons per acre.

When the label states a *range* of rates of pesticide per acre, such as Pounce used at 6 to 12 ounces per acre, then grower experience with factors such as pest density and tree size can be considered in deciding whether the low end of the rate range can be used or if it is necessary to go to the high end, or an intermediate rate.

**Advantage of Method 1:** It is easy, because no calculations are needed.

**Disadvantage of Method 1:** The rate per acre is not given on the label of many pesticide products used on fruit crops, so this method is often not possible.




Figure 4. Airblast sprayer.



**Recommendation:** Use this method whenever possible. **Note:** This method is recommended only in cases where the rate on the label is stated *only* as a rate per acre. On many labels, the rate is given two ways — as the rate per 100 gallons and as a full (maximum) rate per acre based on the standard conversion (as explained in Method 2).

**Method 2: Use the full rate per acre as calculated by the standard conversion from the dilute rate.**

When a pesticide label states the rate as an amount of pesticide per 100 gallons of water, but you want to make a concentrate application and you need to know the equivalent amount of pesticide per acre, then you can make the standard conversion to the full rate per acre. The full rate is sometimes referred to as the *concentrate rate*. This full rate per acre should be thought of as the *maximum* amount of pesticide to use per acre.

Make the standard conversion by *multiplying the amount of pesticide per 100 gallons times the standard dilute volume of water per acre*. In the case of apples, the standard dilute volume per acre is usually defined as 400 gallons per acre. The amount of pesticide per 100 gallons, times 400 gallons per acre, gives you the full amount of pesticide needed per acre of apples. This is based on the old assumption, as mentioned near the beginning of this bulletin, that it takes 400 gallons of spray mix for a thorough dilute application to an acre of large apple trees.

$$\left( \frac{\text{amount of pesticide}}{100 \text{ gallons of water}} \right) \times \left( \frac{\text{standard dilute volume of water}}{\text{acre}} \right) = \text{the full rate of pesticide per acre}$$

For example, if the dilute rate for Captan 50WP on apples is 1.5 pounds per 100 gallons of water, then the full rate per acre is 1.5 pounds per 100 gallons, times 400 gallons water per acre, which equals 6 pounds Captan per acre.

$$\left( \frac{1.5 \text{ pounds}}{100 \text{ gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{acre}} \right) = \frac{6 \text{ lbs. Captan}}{\text{acre}}$$

**Note:** It is these full rates per acre calculated by the standard conversion that we list in the column called “rate per acre” in our Ohio tree fruit spray guide. Again, this full rate per acre should be thought of as the *maximum* amount of pesticide to use per acre.

### ***Summary of Full Rates***

$$\begin{array}{l} \text{full rate} \\ \text{of pesticide} \\ \text{per acre of } \mathbf{apples} \end{array} = \left( \frac{\text{amount} \\ \text{of pesticide}}{100 \text{ gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{acre}} \right)$$

$$\begin{array}{l} \text{full rate} \\ \text{of pesticide} \\ \text{per acre of } \mathbf{peaches} \end{array} = \left( \frac{\text{amount} \\ \text{of pesticide}}{100 \text{ gal. water}} \right) \times \left( \frac{300 \text{ gal. water}}{\text{acre}} \right)$$

$$\begin{array}{l} \text{full rate} \\ \text{of pesticide} \\ \text{per acre of } \mathbf{berries} \end{array} = \left( \frac{\text{amount} \\ \text{of pesticide}}{100 \text{ gal. water}} \right) \times \left( \frac{200 \text{ gal. water}}{\text{acre}} \right)$$

**Advantage of Method 2:** It is relatively easy to calculate, and the calculations have already been done and are listed in our Ohio tree fruit spray guide.

**Disadvantage of Method 2:** It can result in using higher than necessary rates, especially for small trees.

**Recommendation:** Do not use this method if you want the most economical rate; it is better to use Method 1 or 4 or 5.

**Method 3: Use the full rate per acre less 20 or 25%.**

Once concentrate spraying became a common practice several decades ago, experienced fruit growers and researchers noticed that effective insect and disease control was often obtained when using a lower rate than the full rate per acre. It became a common practice to use 20 or 25% less than the full rate per acre.

For example, for an application to apples of Imidan 70WP, which has a labelled rate of 1 pounds per 100 gallons:

The full rate by the standard conversion =

$$(1 \text{ lb. pesticide}/100 \text{ gal. water}) \times (400 \text{ gal. water/acre}) = 4 \text{ lbs. Imidan/acre}$$

To figure 20% less:

$$(4 \text{ pounds per acre}) \times (0.20) = 0.8 \text{ lb.}$$

$$(4 \text{ pounds per acre}) - (0.8 \text{ pounds}) = 3.2 \text{ pounds per acre}$$

A quicker way to get the same answer is to take 80% of the full rate:

$$(4 \text{ pounds per acre}) \times (0.80) = 3.2 \text{ pounds per acre}$$

Our older spray guides (1986 and earlier) included a 20% deduction in their published rates per acre. **Note:** Our current Ohio tree fruit spray guide does *NOT* use this 20% deduction in the rates per acre.

**Advantage of Method 3:** It means lower costs per acre for pesticides than if using the full rate per acre.

**Disadvantage of Method 3:** The 20% rule can work well for some products or some pest targets but not for others; research results are not available to determine exactly when this rule works and when it does not. It might mean that the rate being applied is below the rate stated on the label, thus the label directions are technically not being followed. If a below-label rate is used, the manufacturer cannot be blamed if the product does not perform adequately.

**Recommendation:** Growers whose experience gives them confidence in using lower rates can certainly use this 20% reduction, but keep liability issues in mind if using lower than the label rate. It is better to use Method 1 or 4 or 5.



### **Introduction to Methods 4 and 5:**

**Use a pesticide rate per acre customized to your fruit operation, based on tree-row volume.**

When a label states the rate of pesticide per 100 gallons of water, then the rate of pesticide per acre can be customized for *your* sprayer and *your* orchard, by following either of two methods based on tree-row volume. With either method, first you need to determine your dilute volume of water per acre, as described previously (pages 4-6). Once you know your dilute volume, then you can determine your pesticide rate per acre either directly by tree-row volume (Method 4) or by the percentage-of-standard method (Method 5). Whether to use Method 4 or Method 5 is just a matter of personal preference; they are both based on the same principle.

**Advantage of Methods 4 and 5:** Spray costs are reduced by not applying more product than necessary.

**Disadvantage of Methods 4 and 5:** These are more complicated to calculate. However, most calculations can be done once per year; there is no need to recalculate for every spray.

**Recommendation:** Method 4 or 5 is best whenever the rate per acre is not provided on the label. In other words, these methods are best whenever Method 1 does not apply.

### **Method 4: Use a pesticide rate customized to your fruit operation based directly on the tree-row volume method.**

Simply take *your* dilute volume of water per acre and multiply it by the dilute rate of pesticide per 100 gallons of water. This is a customized rate, because your dilute volume is based on the size and spacing of your trees.

$$\left( \begin{array}{c} \text{the dilute rate} \\ \text{of pesticide} \\ \text{per 100 gallons of water} \end{array} \right) \times \left( \begin{array}{c} \text{your dilute} \\ \text{volume of} \\ \text{water per acre} \end{array} \right) = \begin{array}{c} \text{your} \\ \text{customized} \\ \text{pesticide rate per acre} \end{array}$$

For example, for application of Imidan 70WP at a dilute rate of 1 pound per 100 gallons, in an orchard that needs 180 gallons per acre to treat to runoff: take 1 pound per 100 gallons, times 180 gallons per acre, which equals 1.8 pounds. You thus need 1.8 pounds of Imidan 70WP for each acre. You can see that this is much less product than if you had used just the full rate, which is 4 pounds of Imidan per acre.

$$\left( \frac{1 \text{ pound}}{100 \text{ gal. water}} \right) \times \left( \frac{180 \text{ gal. water}}{\text{acre}} \right) = 1.8 \text{ pounds Imidan per acre}$$

**Method 5: Use a pesticide rate customized to your fruit operation by the tree-row volume method and the percentage-of-standard method.**

First, divide your dilute volume of water per acre by the standard dilute volume of water per acre, which gives you the percentage of standard for your trees. How to determine your dilute volume per acre was detailed on pages 4-6. The standard dilute volume for apples is 400 gallons per acre as defined on pages 1, 3, and 10.

$$\frac{\text{your dilute volume of water per acre}}{\text{standard dilute volume of water per acre}} = \text{the percentage of standard for your trees}$$

For example, if you determined that it takes 180 gallons per acre for a dilute application to your apple trees, then your percentage of standard = 180 gallons per acre, divided by 400 gallons per acre = 45%. Your trees are 45% of standard.

$$\frac{180 \text{ gal. water per acre}}{400 \text{ gal. water per acre}} = 0.45 \text{ Your trees are 45\% of standard.}$$

An alternate way to get the percentage of standard is to use tree size and spacing in the chart on page 19. For example, for trees 12 feet wide and 10 feet tall at 20-foot row spacing, the trees are 46% of standard if well-pruned, as found in the column for minimum dilute volume, or 65% of standard if unpruned, as found in the column for maximum dilute volume.

Second, determine the amount of pesticide to use by *multiplying your percentage of standard by the full rate per acre*. Remember that the full rate per acre = amount of pesticide per 100 gallons times 400 gallons water per acre of apples, as explained previously in Method 2 (page 10).

$$\left( \frac{\text{your percentage of standard}}{\phantom{0.45}} \right) \times \left( \frac{\text{the full pesticide rate per acre}}{\phantom{0.45}} \right) = \text{the amount of pesticide to use per acre}$$

For example, if your trees are 45% of standard and you need to apply Imidan 70WP, which has a dilute rate of 1 pound per 100 gallons, then the full rate by the standard conversion is 1 pound per 100 gallons, times 400 gallons per acre, which equals 4 pounds per acre. Take 45% of the full rate: 45% of 4 pounds per acre is 0.45 times 4 equals 1.8 pounds per acre.

The full rate by the standard conversion:

$$\left( \frac{1 \text{ pound}}{100 \text{ gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{acre}} \right) = 4 \text{ pounds Imidan per acre}$$


45% of the full rate:

$$45\% \text{ of } 4 \text{ pounds per acre} = 0.45 \times 4 = 1.8 \text{ pounds Imidan per acre}$$

## Examples for Review

To help review the information presented in the last few pages, here is a series of four sample calculations, all based on Provado 1.6F insecticide, which is labeled for application to apples for leafminer control at a dilute rate of 2 fluid ounces per 100 gallons. The Provado label does not state a rate per acre.

**Example 1:** How much Provado 1.6F should a grower use per acre for an orchard of big old apple trees, for a *dilute* application, if these trees require 400 gallons of water per acre to the point of runoff?




$$(\text{dilute rate}) \times (\text{dilute volume}) = (\text{amount of product per acre})$$

$$\left( \frac{2 \text{ oz.}}{100 \text{ gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{acre}} \right) = 8 \text{ oz. per acre}$$

Example 1.

**Example 2:** How much Provado 1.6F should a grower use per acre for an orchard of semidwarf apple trees, for a *dilute* application, if these trees require 180 gallons of water per acre to the point of runoff?




$$(\text{dilute rate}) \times (\text{dilute volume}) = (\text{amount of product per acre})$$

$$\left( \frac{2 \text{ oz.}}{100 \text{ gal. water}} \right) \times \left( \frac{180 \text{ gal. water}}{\text{acre}} \right) = 3.6 \text{ oz. per acre}$$

Example 2.



**Example 3:** How much Provado 1.6F should a grower use per acre for an orchard of semidwarf apple trees, for a *concentrate* application, if these trees require 180 gallons of water per acre to the point of runoff, and the grower's airblast sprayer uses 60 gallons of water per acre? And what concentration is this?



Example 3.

$$(\text{dilute rate}) \times (\text{dilute volume}) = \text{amount of product per acre}$$

$$\left( \frac{2 \text{ oz.}}{100 \text{ gal.}} \right) \times \left( \frac{180 \text{ gal.}}{\text{acre}} \right) = 3.6 \text{ oz. per acre}$$

$$\frac{\text{dilute volume}}{\text{concentrate volume}} = \text{concentration}$$

$$\frac{180}{60} = 3 \quad \text{This is a 3X concentration.}$$


You might have noticed that the block of semidwarf trees used in Examples 2 and 3 required the same amount of Provado per acre for either a dilute or a concentrate application, but the amount of *water* used per acre was different for the two types of applications.

**Example 4:** How much Provado 1.6F should a grower use per acre for an orchard of semidwarf apple trees, for a *concentrate* application, if these trees are in rows 18 feet apart, the tree canopy width is 10 feet, and the tree height is 10 feet? And what spray concentration is used when an airblast sprayer applies 85 gallons per acre?

First, check the chart on page 19. For 18-ft. rows and trees 10-ft. wide and 10-ft. tall, your dilute volume would be 169 gallons per acre.

dilute volume = 169 gal. per acre, based on the chart on page 19

For the final step multiply the dilute rate by the grower's dilute volume to determine the amount of pesticide to use per acre.



Example 4.

$$(\text{dilute rate}) \times (\text{your dilute volume}) = \text{amount of product per acre}$$

$$\left( \frac{2 \text{ oz.}}{100 \text{ gal.}} \right) \times \left( \frac{169 \text{ gal.}}{\text{acre}} \right) = 3.4 \text{ oz. per acre}$$

Another way to do the final step is to note in the tree-row volume chart that the trees are 42% of standard. Then take 42% of the full rate of Provado.

$$\begin{array}{rcl} \text{amount of pesticide} & \times & \text{standard} \\ \text{per 100 gal. water} & & \text{dilute volume} \\ & & \text{of water per acre} \\ & & = \\ & & \text{full rate} \\ & & \text{of pesticide} \\ & & \text{per acre} \end{array}$$

$$\left( \frac{2 \text{ oz.}}{\text{per 100 gal. water}} \right) \times \left( \frac{400 \text{ gal. water}}{\text{per acre}} \right) = 8 \text{ oz. per acre (the full rate)}$$

$$42\% \text{ of the full rate: } (8 \text{ oz. per acre}) \times (0.42) = 3.4 \text{ ounces per acre}$$

The concentration is 169 gallons per acre divided by 85 gallons per acre which equals approximately 2, so it is a 2X application.

$$\frac{\text{dilute volume}}{\text{concentrate volume}} = \text{concentration}$$

$$\frac{169 \text{ gal. per acre}}{85 \text{ gal. per acre}} = \text{approximately 2} \quad \text{This is a 2X concentration.}$$

# *Spraying in Different Seasons and in Different Orchards*

## *Managing Different Orchard Blocks*

Keep in mind that if you have several blocks of fruit trees that vary in tree size and spacing, then your dilute volume, your concentrate volume, and your concentration factor probably vary from block to block. You might need to adjust your application accordingly from block to block. The calculations should also be re-done periodically as trees grow from year to year.

## *Seasonal Adjustments*

During the growing season, the tree canopy changes from a relatively thin canopy during the dormant and delayed dormant periods in the spring, to a moderately thick canopy by petal-fall, to a maximum density after terminal shoots are fully developed by midsummer. Thorough coverage is more difficult to achieve when the canopy is thick. The dilute volume and concentrate volume required can be adjusted to allow for these canopy changes if the grower notices that one all-purpose volume is not always adequate.

## *Recommendation*

Be sure to evaluate fruit quality on the packing line after harvest. If the grower's spray program is not adequately controlling all insect and disease problems, then spray rates and volumes are factors that the grower should re-evaluate for the following year.

## *Summary*

Appendix 1 is the tree-row volume chart, which shows the dilute volume of spray mixture per acre required to spray tree fruit of various tree sizes and spacings, and the equivalent percentage of standard dilute volume, assuming that trees are mature enough to fill the rows. Appendix 2 summarizes how much water and pesticide to use in various situations. Appendix 3 gives a glossary of terms used in this bulletin.

## *Acknowledgments*

Thanks to Karen Magnuson for making the illustrations, and to Joanne Kick-Raack, Frank Hall, Joe Kovach, Mike Ellis, Ric Bessin, Rick Foster, Ted Gastier, and Dave Ferree for review comments.

**Editor:** Joy Ann Fischer, Communications & Technology

**Graphic Designer:** Sandra Born, Communications & Technology



## Appendix 1: Tree-Row Volume Chart.

This chart shows the dilute volume of spray mixture per acre required to spray tree fruit of various tree sizes and spacings, and the equivalent percentage of standard dilute volume, assuming that trees are mature enough to fill the rows.

Distance between rows (feet)	Tree canopy width (feet)	Tree height (feet)	Tree row volume per acre (cubic feet, rounded to nearest 1,000)	Your dilute spray volume (gallons per acre)		Your dilute spray volume as a percentage of standard dilute volume			
				Minimum <sup>1</sup>	Maximum <sup>2</sup>	Pome Fruit (base 400 g.p.a.) <sup>3</sup>		Stone Fruit (base 300 g.p.a.) <sup>3</sup>	
						Minimum <sup>1</sup>	Maximum <sup>2</sup>	Minimum <sup>1</sup>	Maximum <sup>2</sup>
40	22	22	527,000	369	527	92%	132%	123%	176%
30	20	20	581,000	407	581	102%	145%	136%	194%
30	20	15	436,000	305	436	76%	109%	102%	145%
26	16	12	322,000	225	322	56%	80%	75%	107%
24	14	12	305,000	213	305	53%	76%	71%	102%
22	14	12	333,000	233	333	58%	83%	78%	111%
20	15	12	392,000	274	392	69%	98%	91%	131%
20	12	14	366,000	256	366	64%	92%	85%	122%
20	12	12	314,000	220	314	55%	78%	73%	105%
20	12	10	261,000	183	261	46%	65%	61%	87%
20	10	10	218,000	152	218	38%	54%	51%	73%
19	11	10	252,000	177	252	44%	63%	59%	84%
18	12	12	348,000	244	348	61%	87%	81%	116%
18	10	10	242,000	169	242	42%	60%	56%	81%
18	8	8	155,000	108	155	27%	39%	36%	52%
17	9	9	208,000	145	208	36%	52%	48%	69%
16	8	8	174,000	122	174	30%	44%	41%	58%
15	7	8	163,000	114	163	28%	41%	38%	54%
14	6	9	168,000	118	168	29%	42%	39%	56%
14	6	8	149,000	105	149	26%	37%	35%	50%
14	6	7	131,000	91	131	23%	33%	30%	44%
13	6	7	141,000	99	141	25%	35%	33%	47%
12	6	6	131,000	91	131	23%	33%	30%	44%
12	3	8	87,000	61	87	15%	22%	20%	29%

<sup>1</sup> Minimum: For most orchards that are regularly pruned (0.7 gal per 1,000 ft<sup>3</sup>).

<sup>2</sup> Maximum: For unpruned orchards or unusually thick canopies (1.0 gal per 1,000 ft<sup>3</sup>).

<sup>3</sup> g.p.a. = gallons per acre.

## Appendix 2: Summary of How Much Water and Pesticide to Use for Different Types of Spray Applications to Apple Orchards.

Type of Application	Amount of Water Per Acre	Amount of Pesticide Per Acre
Standard dilute application	Use 400 gallons per acre, which is enough to cover leaves of large trees to the point of runoff.	Use full rate of pesticide = (amount of pesticide per 100 gallons of water) x (400 gallons per acre)
Dilute application customized to smaller trees	Use enough to cover leaves to the point of runoff, as determined by experience and experimenting with your sprayer in your orchard.	Use (amount of pesticide per 100 gallons of water) x (your customized dilute volume of water per acre)
	OR: Use amount estimated from the tree-row volume chart (see pages 4 and 19).	
	OR: Use amount determined by tree-row volume equations (pages 4-6).	
Standard concentrate (low-volume) application	Use enough to provide adequate coverage of the canopy, based on experience and experimenting with your sprayer in your orchard; likely to be 40–80 gal per acre.	Use amount of pesticide per acre as stated on pesticide product label.
		OR: Use full rate of pesticide = (amount of pesticide per 100 gallons of water) x (400 gallons per acre)
		OR: Use full rate less 20 or 25% if your experience shows that control is adequate with this adjustment.
Concentrate (low-volume) application customized to smaller trees	Use enough to provide adequate coverage of the canopy, based on experience and experimenting with your sprayer in your orchard; likely to be 40–80 gal per acre.	Use the amount of pesticide per acre as stated on pesticide product label.
		OR: Use amount based directly on tree-row volume = (dilute rate per 100 gallons) x (your dilute volume per acre)
		OR: Use amount based on tree-row volume and percentage of standard = (full rate per acre) x (your dilute volume per acre divided by the standard dilute volume per acre)

## Appendix 3: Glossary of Terms

### 1. Standard trees

Fruit trees that are large (about 20 feet tall and 20 feet wide) and widely spaced (rows about 30 feet apart) within the orchard; it is the term used by horticulturalists for the type of apple trees that were grown for many years before dwarfing rootstocks became available.

### 2. Types of orchard pesticide applications

*dilute application*: application of pesticide to fruit trees *to the point of runoff*, that is, until liquid begins to drip off the leaves; application is made by either an airblast sprayer or a handgun sprayer.

*concentrate application* (also called *low-volume application*): application of pesticide to fruit trees by an airblast sprayer that produces fine droplets that cover foliage very well without the large volume needed to reach the point of runoff.

### 3. Spray volumes

*dilute volume*: the number of gallons of water it takes to cover an acre of fruit trees to the point of runoff.

*standard dilute volume*: the number of gallons of water it takes to cover an acre of standard (large) fruit trees to the point of runoff; for apple or pear trees, the standard dilute volume is 400 gallons of spray mix per acre. For peach, plum, and cherry, 300 gallons per acre is the standard dilute volume. For strawberries, brambles, blueberries, and grapes, 200 gallons per acre is the standard dilute volume.

*your customized dilute volume*: the number of gallons of water it should take to cover one acre of *your* trees to the point of runoff, usually 100 to 200 gallons per acre for semidwarf or dwarf apple trees.

*your concentrate spray volume*: the number of gallons of water per acre *your* airblast sprayer uses to adequately treat *your* orchard for a low-volume application, for whatever speed, pressure, and nozzle arrangement you prefer to use, usually 40 to 80 gallons per acre.

*concentration* (or *concentrate factor*): *your* dilute volume of water per acre divided by *your* concentrate volume of water per acre.

### 4. Rates of pesticide products

*dilute rate*: the amount of pesticide that should be used to make a *dilute* application to the point of runoff with either a handgun sprayer or an airblast sprayer; usually expressed as an amount of pesticide to be mixed per 100 gallons of water.

*full rate*: the *maximum* amount of pesticide to use per acre; calculated by multiplying the dilute rate (equals the amount of pesticide per 100 gallons) by the standard dilute volume per acre (equals 400 gallons per acre for apples).

*concentrate rate*: the amount of pesticide used per acre when making a concentrate (low-volume) application; this might be equal to or less than the full rate per acre.

### 5. Tree-row volume:

The amount of space occupied by fruit trees; calculated by tree height, tree width, and tree spacing; used as the basis for determining the amount of water and pesticide needed to adequately cover the trees with spray.



*References to products in this publication are not intended to be an endorsement to the exclusion of others that may be similar. Any person using products mentioned in this publication assumes full responsibility for their use in accordance with current directions of the manufacturer. The author and Ohio State University Extension assume no liability resulting from the use of these products.*